



# X-Lite v3.0 Sample Configuration

## Revision History

Date	Revision	Description
February 2007	V1.0	First Draft

## Table of Contents

1. Introduction	1
2. Sample Configuration	1
2.1. SIP Account Settings	1
2.1.1. Account Properties – Accounts	2
2.1.2. Account Properties – Advanced	2
2.2. Options	3
2.2.1. Options – General – Application	3
2.2.2. Options – General – Devices	3
2.2.3. Options – Advanced – Audio Codecs	4
2.2.4. Options – Advanced – Quality of Service	4

## 1 Introduction

This document gives a basic sample configuration of X-Lite V3.0 (Build 1106e for Windows) when using MyNetFone's Service.

### Note:

We are sorry about we do not provide any quality guarantee when using X-lite on MyNetFone service because the Codec that we prefer is G.729 but X-lite V3.0 doesn't support it.

We recommend our customer using MyNetFone [SoftClient](#) because it was designed for our service. It's totally FREE for our customer, Please visit <http://www.myfone.com.au/support/> for more details.


## 2 Sample Configurations

### 2.1 SIP Account Settings

1. To manage SIP accounts, click  at the top of the phone and select **SIP Account Settings**. The SIP Account window appears, showing the account that the user has set up.
2. If no account is listed, click **Add**



## 2.1.1 Account Properties - Account



**Properties of Account1**

Account | Voicemail | Topology | Presence | **Advanced**

**User Details**

Display Name: 09100000

User name: 09100000

Password: ●●●●●●

Authorization user name: 09100000

Domain: sip01.mynetfone.com.au

**Domain Proxy**

Register with domain and receive incoming calls

Send outbound via:

domain


proxy Address: sip01.mynetfone.com.au

target domain

Dialing plan: #1{a.T;match=1;prestrip=2;}

OK Cancel Apply

## 2.1.2 Account Properties - Advanced



**Properties of Account1**

Account | Voicemail | Topology | Presence | **Advanced**

**Register Settings**

Reregister every: 240 seconds

Min. time: 20 seconds

Max. time: 120 seconds

**Advanced Options**

Send SIP keep-alives  Use rport

Enable session timers Default session time: 60 seconds


Session Timer Preference: None

OK Cancel Apply

## 2.2 Options


1. To manage X-Lite features and options, click  at the top of the phone and select **Options**.

### 2.2.1 Options - General - Application




### 2.2.2 Options - General - Devices

Change all the Speaker and Microphone devices to your USB phone audio device.




### 2.2.3 Options - Advanced - Audio Codecs

To manage the advance X-Lite options, click the Advanced tab in the lower left hand column.



### 2.2.4 Options - Advanced - Quality of Service



Available QoS Service types:

- Best Effort, Controlled Load, Guaranteed, Qualitative

\* All X-Lite information belongs to CounterPath Solutions, Inc. All rights reserved.

<http://www.xten.com>